



USB Flash Security +g

USB Flash Security ++g

USB Flash Security #g

USB Flash Security ##g

Quick Start

Before use USB Flash Security

1. [USB Flash Security] has 9 editions. [License]/[Capacity of USB disk]/[Number of USB drive can be installed by one PC] is different by each edition. Please confirm the difference of each edition in our homepage (<http://kashu-sd.co.jp/en>) or confirm it in the help after install this software. 4 **product editions for group users** mainly are introduced in this file.
2. Please acknowledge being not able to assume all responsibilities even if a direct or indirect damage is cause by using this software.

This file introduce the basic of installing security by several patterns and it is help the user who use [USB Flash Security] first time to use the function faster. The screenshot in this help is screen of [USB Flash Security ##g] mainly. If there is not any explain of screenshot, it is common with all of editions except icon and title.

[Contents]

[Install on PC](#)

[Install on USB Flash Drive](#)

[Method of unlock security 1](#)

[Method of unlock security 2](#)

[Method of unlock security 3](#)

[Copy safely remove tool](#)

[Uninstall from USB Flash Drive](#)

[Uninstall from PC](#)

Install on PC


The name of setup are the following file names. Depending on the PC requirement ".exe" may be hidden. Run (double-click) the file to start the installation.

Edition	File name
+g	UsbEntPg_Setup.exe
++g	UsbEntPPg_Setup.exe
#g	UsbEntSg_Setup.exe
##g	UsbEntSSg_Setup.exe


1. Please open the compress (zip form) folder, run (double-click) the setup file. When the following screen displayed please click [Run] button. If the following screen did not display please go to the next step.




2. When User Account Control screen displayed, please click [Yes] button. If the following screen did not display please go to the next step.




3. When the following screen display, please click the top larger button to start installation before the setup screen display.




4. When [Welcome to the USB Flash Security xxx Setup Wizard] display please click [Next] button.




5. When [License Article] screen display, please read the license article, and if you agree with this license article, please click the [Agree], and click [Next] button. In other cases please click [Cancel] button. (If you don't agree with license article, you are not allowed to you the software.)



6. When [Confirm Installation] display, please click [Next] button to start installation.



7. When [Installation Complete] display, please click [Close] button. If installation complete, shortcut will be created in program menu and desktop automatically.



[Back to contents](#)


Install on USB Flash Drive

USB Flash Drive will be formatted and data in the USB Flash Drive will be deleted by installing security to the USB Flash Drive, please backup your data to the other hard disk before install security.


1. After installation, please run (double-click) the shortcut created on desktop.




2. At first start screen display. A short description will display, please read it and click [OK] button. If do not need start screen display again, please check with [Don't display again]. And start screen won't display again next time.



3. When license register screen display, please click [Trial] button to go to next.



4. Administrator password setting screen will display by first run. Please set the administrator password. Administrator password is not only for start the software installed in PC, it also can be used to unlocked security. We recommend setting password more complicated (Upper case letters, lower case letters, number mixed) and longer (Max 32 characters). However, administrator password is necessary to start this software, so please note your password and do not forget it. Administrator password can not be changed anymore in order to protect it against changing by malicious one. Please input the same password twice for confirming. After set the password and hint, please click [OK] button and the main screen of this software will display.




The image shows a dialog box titled "Administrator password setting". It contains two main sections. The first section is titled "Please set the administrator password." and includes two text input fields labeled "Password" and "Confirm", a checkbox labeled "Display the password", and the instruction "Please input a same password twice for confirmation." The second section is titled "Please set a hint for the password to remember you." and includes a text input field labeled "Hint" and the instruction "It will display when move the mouse cursor to the password field in the screen of administrator password inputting." At the bottom of the dialog are "OK" and "Cancel" buttons.

*Please input same password twice.

*Password distinguishes between upper case letters and lower case letters.


*Password will be saved in PC.

5. Administrator password input screen will display after 2nd. Hint will display when move mouse cursor to password field in the screen. After input administrator password and click [OK] button main screen of this software will display.




The image shows a dialog box titled "USB Flash Security##g". It contains a text input field labeled "Password" with a cursor inside. Below it is a checkbox labeled "Display the password". A tooltip with the text "Name of pet!" is positioned over the "Display the password" checkbox. At the bottom of the dialog are "OK" and "Cancel" buttons.

6. If there is not any USB disk connect to the PC, the following screen will display.




7. Please plug the USB Flash Drive to install security. When USB Flash Drive display please select the USB Flash Drive and click [Install] button.



8. When install security, data in USB Flash Drive will be deleted. Please confirm the screen, if data in USB Flash Drive may be deleted, please click [OK]. If not, please click [Cancel] to stop installation.



9. When security setting screen display, please input password and hint and click [OK] button.



*Password distinguishes between upper case letters and lower case letters.

*Password will be saved in USB Flash Drive.


*+g doesn't have unlock page.

*Please confirm the details of setting in [Disk Security Settings] of setting menu.


10. When install confirm screen display, please set the check box checked after you confirmed the contents, then you can begin the installation.




11. Install software on USB Flash Drive. Please wait for a moment.




12. When install complete screen display, please click [Close] button.




13. autorun.inf and UsbEnter.exe will copy to USB Flash Drive when install complete.



14. The capacity will be [0.00GB] in USB Flash Security main screen that installed on PC, if install security normally.




15. The capacity will be [549KB] in property of USB drive, if install security normally.




[Back To contents](#)

Method of unlock security 1


1. Please unplug and plug USB Flash Drive to PC. Please show the file in USB Flash Drive in explorer. Please select `UsbEnter.exe` and run it.



2. When screen of release tool display, please input password set on USB Flash Drive and click [OK] button.




3. If screen of [Please wait] disappear without any error message, USB Flash Drive is unlocked and it can be used as normal.



[Back To contents](#)

Method of unlock security 2

1. Please unplug and plug USB Flash Drive to PC. When the screen of auto-run display, please run (double-click) release tool.




*The screen won't display if Service Pack is older than Service Pack 2 on Windows XP.

*If setting of auto-run is disabled, the screen won't display.


*Screen of auto-run will display on Windows 7, but release tool won't display in the screen.

*If screen of auto-run doesn't display, please unlock security by [Method of unlock security 1](#).

2. When screen of release tool display, please input password set on USB Flash Drive and click [OK] button.




3. If screen of [Please wait] disappear without any error message, USB Flash Drive is unlocked and it can be used as normal.



[Back To contents](#)

Method of unlock security 3

1. Please unplug and plug USB Flash Drive to PC. Please run explorer, and right-click the USB Flash Drive. Then select release tool in the menu to run it.




*The menu won't display if Service Pack is older than Service Pack 2 on Windows XP.


*Release tool won't display in the menu on Windows 7 by right-click USB Flash Drive in explorer.

*If release tool doesn't display in the menu which displayed right-click USB Flash Drive in explorer, please unlock security by [Method of unlock security 1](#).

2. When screen of release tool display, please input password set on USB Flash Drive and click [OK] button.



3. If screen of [Please wait] disappear without any error message, USB Flash Drive is unlocked and it can be used as normal.




[Back To contents](#)


Copy safely remove tool

Copy the tool (UsbExit.exe and autorun.inf) to remove USB Flash Drive from PC. safely remove function is not necessary, but we recommend using this tool, because safely remove tool has several functions for [USB Flash Security]. If you don't need this tool, please delete it.


1. Please connect the USB Flash Drive and unlock security.




2. Please select [Copy of Safely Remove tool] in operation menu.




3. When [Processing finished normally.] display, [Safely remove tool] has been copied to USB Flash Drive.



4. autorun.inf and UsbExit.exe are created on USB Flash Drive.



5. Run (double-click) UsbExit.exe, and the following screen will display. If click [Hide the protected area], it will hide the protected area and show the unprotected area. If click [Safely remove], USB Flash Drive will be removed from PC safely.




[Back To contents](#)


Uninstall from USB Flash Drive

Uninstall security and restore USB Flash Drive. It is necessary to do [Uninstall] function in operation menu for restore USB Flash Drive. Windows format can not restore USB Flash Drive. Data in USB Flash Drive will be deleted by do this operation, so if necessary please backup your data and do this operation.

1. Please run [USB Flash Security] installed on PC, and plug the USB Flash Drive installed security to PC.




2. Please select [Uninstall] in operation menu.




- All of data will be deleted when uninstall security from USB Flash Drive. If data is necessary, please click [Cancel], if not please click [OK].



- The following screen will display, if processing finished normally. Please click [OK] button.



- After uninstall security from USB Flash Drive, the full capacity will display in screen of [USB Flash Security] installed on PC.




[Back To contents](#)


Uninstall from PC

Delete this software from PC. USB Flash Drive can't be restored by deleting security from PC automatically. Please do [\[Uninstall from USB Flash Drive\]](#) before delete this software from PC for restoring USB Flash Drive. Please use [\[Add or Remove Programs\]](#) in [\[Control Panel\]](#) on XP and [\[Uninstall a Programs\]](#) in [\[Control Panel\]](#) on Windows Vista / 7 to uninstall it form PC. The following screen shot is uninstalling this software from Windows 7.


1. Please start Control Panel form start menu.




2. Please select [\[Uninstall a Program\]](#) in Control panel.



3. Please select this software in the screen of [Uninstall a Program] and click [Uninstall] button.



4. When the confirm screen display, please click [Yes] button to uninstall this software from PC.



[Back to contents](#)